



Winprint Hylafax for Windows Vista / 7


1. Deactivating UAC

First you'll need to deactivate UAC (User account control).

You can find it under control panel > User accounts > Change User Account Settings



Here you can set the UAC to never notify in Windows 7 or just uncheck it in Windows Vista




After this you'll need to restart the computer and login again as Administrator.



2. Installing Winprint HylaFAX


You can download the software by following this link:

<http://info.hexacom.be/Software/Hylafax%20Windows7/WinprintHylaFAX-1.2.9.zip>

Unzip the file and double click the WinprintHylaFAX-1.2.9.exe file.







The HylaFAX software is now installed and you can now proceed to setup the virtual printer.


3. Setting up the virtual printer

You can download the drivers for this printer by following this link:


http://info.hexacom.be/Software/Hylafax%20Windows7/KMPPD64PSMINIWin_1310090EN.ZIP

Extract the file to a logical location (like c:\printer driver)


Go to start > Devices and Printers




Click on Add a Printer




Click on 'Add a local printer'




Select 'create a new port' and select Winprint Hylafax in the drop-down menu, then click next.




Enter HylaFAX as port name then click OK.




On the next screen click on 'have disk'




Click browse...




Select the folder you unzipped under c:\printer driver and select KMMulti, then click open.




Click OK



Select 'Konica Minolta bizhub 40P PPD' and click next




Set the name to Fax over VOB then click next.




When getting this warning, click on install anyway.




This screen will appear during installation.



Set to 'Do not share this printer' and click next.




Click finish to finish the installation.




4. Setting up the Printer Port


Go to start > Devices and Printers



Right-click on the printer you just installed (Fax over VOB) and click Printer properties.



Go to the ports-tab, select Hylafax and click configure Port.



Enter the information like in the screenshot and enter your username and password that you received from Hexacom.

Configure HylaFAX Client

HylaFAX Server Address:

Ignore PASV IP address:

Username:

Password:

Default Notify:

Notification:

Modem:

Address Book Format:

Address Book Directory:

Page Size:

Resolution:

Click OK and close all windows.

Now you can reactivate UAC (See step 1) and reboot the computer.